



IMT3312 AIRLINE RESERVATION AND TICKETING

WEEK 1

SIGN-IN



<https://www.training.sellingplatformconnect.amadeus.com/>



Activate Windows
Go to PC settings to activate Windows

SIGN-IN

Selling Platform Connect

Unleash your business!

amadeus

Sign In

Language:

Please enter your details to sign in.

User name:

Office ID:

Password:

[Forgot your password?](#)

Remember me

Welcome



Welcome to **Amadeus Selling Platform Connect** - the next-generation fully cloud-based booking and fulfillment platform that is designed to free you from technology constraints so you can put your passion to work

[Why Amadeus Selling Platform Connect](#)

Activate Windows

SIGN-IN

Sign In

Language:

Please enter your details to sign in.

Username:

Office ID:

Password:

[Forgot your password?](#)

Remember me

English (UK)

rsutr100

BKKTG350M

amadeus1

SIGN-IN

Platform Connect
for business!

AMADEUS

The screenshot shows the Amadeus Selling Platform Connect sign-in interface. A modal dialog box titled "Change Expired Password" is open, prompting the user to enter their details and a new password. The dialog contains the following fields and information:

- Title:** Change Expired Password
- Instruction:** Please enter your user details and your new password.
- Username:** rsutrn113
- New Password:** [Redacted with dots]
- Password strength:** Good
- Confirm New Password:** [Redacted with dots]
- Buttons:** Sign In, Cancel

In the background, the sign-in form is partially visible, showing fields for language (English (UK)), username (rsutrn113), and password (BKKTG35...), along with a "Remember me" checkbox and "Sign in" and "Clear" buttons. A watermark "bkk2018" is overlaid on the page. At the bottom, there is a "Welcome to Amadeus Selling Platform Connect" message and a watermark for "Activate Windows".

SIGN-IN

The screenshot displays a web application interface for Qatar Airways. At the top, there is a navigation bar with a logo 'a' and menu items: File, Go To, Settings, Help, and Service Hub. A promotional banner reads "Plus Pattaya from 28 January". The user is identified as "RSUTRN100" with a "Sign out" link and "Last login:" information. Below the navigation bar are buttons for "New Booking File", "New Command Page", and "New Traveller Profile". A search bar contains the text "Retrieve Booking File by name, reference, etc." with a "Retrieve" button and options for "Advanced" and "Your Smart Flows". The main content area is titled "Command Page 1" and is owned by "BKKTG350M". A sidebar on the right, titled "Go To", includes a "Show in Graphic Mode" section with icons for an airplane and a bed, and a "Show Booking File" section. At the bottom, there is a taskbar with "Main Page" and "Command Page 1" tabs, and a footer with "Office ID: BKKTG350M (Training Mode)". An "Activate Windows" watermark is visible in the bottom right corner.

PHONETIC ALPHABET

A = Able

B = Baker

C = Charlie

D = Dog

E = Easy

F = Fox

G = Gorge

H = How

I = Item

J = Jimmy

K = King

L = Love

M = Mike

N = Nan/Nancy

O = Ober

P = Peter

Q = Queen

R = Roger

S = Sugar

T = Tare

U = Uncle

V = Victor

W = William

X = Xray

Y = York

Z = Zebra

DC

To display two-letter code for a country name or country name for a two -letter code.

Example: DC JAPAN -or DC JP

```
Command Page 1
> dcjp

DCJP
JP   JAPAN/ASIA REGION          TC3

JPY  JAPANESE YEN              LOCAL/INTL PUBLISHED

JPN  JAPAN CITIZEN
*TRN*
█
> |
```


DNS

To encode a state or province.

Example: DNS US CA



Command Page 1

```
> DNS US CA
```

```
DNS US CA
```

```
US CA CALIFORNIA/UNITED STATES OF AMERICA
```

```
*TRN*
```



```
>
```

DAN

To display three-letter codes for a city or airport.
Example: DAN PARIS

Command Page 1

> DAN PARIS

```
DAN PARIS
A:APT B:BUS C:CITY G:GRD H:HELI O:OFF-PT R:RAIL S:ASSOC TOWN
PAR C PARIS /FR
A BVA - BEAUVAIS TILLE - 67K /FR
A XCR - CHALONS VATRY -138K /FR
A CDG - CHARLES DE GAULLE - 22K /FR
A LBG - LE BOURGET - 14K /FR
A ORY - ORLY - 16K /FR
A POX - PONTOISE CORMEILLES - 33K /FR
A TNF - TOUSSUS LE NOBLE - 20K /FR
A VIY - VILLACOUBLAY VELIZY - 14K /FR
H JDP - ISSY LES MOULINEAUX HP - 6K /FR
H JPU - LA DEFENSE HELIPORT - 0K /FR
B XEX - AEROGARE DES INV BUS - 0K /FR
B XTT - ARC DE TRIOMPHE BUS ST - 0K /FR
B XGB - MONTPARNASSE BUS STN - 0K /FR
R XHP - GARE DE L'EST RAIL STN - 1K /FR
R XPG - GARE DU NORD RAIL STN - 1K /FR
R XJY - MASSY TGV RAIL STATION - 17K /FR
YP2 G PARIS /FR
PHT C PARIS /USTN
A PHT - HENRY COUNTY - 0K /USTN
*TRN*
)>
```

Scrolling Commands

MD Code = Move Down

Command Page 1

> md

```
PAR C  PARIS                               /FR
A  BVA - BEAUVAIS TILLE                    - 67K   /FR
A  XCR - CHALONS VATRY                     -138K   /FR
A  CDG - CHARLES DE GAULLE                 - 22K   /FR
A  LBG - LE BOURGET                        - 14K   /FR
A  ORY - ORLY                              - 16K   /FR
A  POX - PONTOISE CORMEILLES              - 33K   /FR
A  TNF - TOUSSUS LE NOBLE                  - 20K   /FR
A  VIY - VILLACOUBLAY VELIZY              - 14K   /FR
H  JDP - ISSY LES MOULINEAUX HP            - 6K    /FR
H  JPU - LA DEFENSE HELIPORT               - 0K    /FR
B  XEX - AEROGARE DES INV BUS              - 0K    /FR
B  XTT - ARC DE TRIOMPHE BUS ST            - 0K    /FR
B  XGB - MONTPARNASSE BUS STN              - 0K    /FR
R  XHP - GARE DE L'EST RAIL STN            - 1K    /FR
R  XPG - GARE DU NORD RAIL STN             - 1K    /FR
R  XJY - MASSY TGV RAIL STATION            - 17K   /FR
YP2 G  PARIS                               /FR
PHT C  PARIS                               /USTN
A  PHT - HENRY COUNTY                      - 0K    /USTN
PRX C  PARIS                               /USTX
A  PRX - COX FIELD                         - 0K    /USTX
```

TRN

MU Code = Move Up

Command Page 1

> mu

```
DAN PARIS
A:APT B:BUS C:CITY G:GRD H:HELI O:OFF-PT R:RAIL S:ASSOC TOWN
PAR C  PARIS                               /FR
A  BVA - BEAUVAIS TILLE                    - 67K   /FR
A  XCR - CHALONS VATRY                     -138K   /FR
A  CDG - CHARLES DE GAULLE                 - 22K   /FR
A  LBG - LE BOURGET                        - 14K   /FR
A  ORY - ORLY                              - 16K   /FR
A  POX - PONTOISE CORMEILLES              - 33K   /FR
A  TNF - TOUSSUS LE NOBLE                  - 20K   /FR
A  VIY - VILLACOUBLAY VELIZY              - 14K   /FR
H  JDP - ISSY LES MOULINEAUX HP            - 6K    /FR
H  JPU - LA DEFENSE HELIPORT               - 0K    /FR
B  XEX - AEROGARE DES INV BUS              - 0K    /FR
B  XTT - ARC DE TRIOMPHE BUS ST            - 0K    /FR
B  XGB - MONTPARNASSE BUS STN              - 0K    /FR
R  XHP - GARE DE L'EST RAIL STN            - 1K    /FR
R  XPG - GARE DU NORD RAIL STN             - 1K    /FR
R  XJY - MASSY TGV RAIL STATION            - 17K   /FR
YP2 G  PARIS                               /FR
PHT C  PARIS                               /USTN
A  PHT - HENRY COUNTY                      - 0K    /USTN
```

TRN

)>

DAC

To display the name for a three-character city or airport code.

Example: DAC SFO

```
Command Page 1
> DAC SFO

DAC SFO
A:APT B:BUS C:CITY G:GRD H:HELI O:OFF-PT R:RAIL S:ASSOC TOWN
CITY :
    SFO C  SAN FRANCISCO          /USCA:CALIFORNIA
AIRPORT-HELIPORT :
    SFO A  SAN FRANCISCO INTL     /USCA    -   OK
*TRN*
█
>|
```

DNA

To display two-character code for an airline name,
or airline name from two-character code.

Example: DNA IBERIA -or- DNA IB

```
Command Page 1
```

```
> DNA IB
```

```
DNA IB
```

```
IB/IBE 075 IBERIA
```

```
*TRN*
```

```
█
```

```
>
```

DNE

To display equipment names for three-letter equipment codes, or list of equipments for equipment name.

**Example: DNE AB3 -or-
DNE AIRBUS**

```
Command Page 1
> DNE AIRBUS

DNE AIRBUS
AB3 W AIRBUS INDUSTRIE A300 JET 181-317
ABA W AIRBUS INDUSTRIE A300 (LH CONFIG) N/A 207-275
ABF W AIRBUS INDUSTRIE A300 FREIGHTER JET 0- 0
ABY W AIRBUS INDUSTRIE A300-600 FREIGHTER JET 0- 0
AB6 W AIRBUS INDUSTRIE A300-600/600C JET 207-317
ABB W AIRBUS INDUSTRIE A300-600ST BELUGA JET 0- 0
AB2 W AIRBUS INDUSTRIE A300-B2 N/A 238-298
AB4 W AIRBUS INDUSTRIE A300-B2/B4/C4 JET 211-317
ABM W AIRBUS INDUSTRIE A300-C4 MIXED JET 211-336
ABX W AIRBUS INDUSTRIE A300B4/C4/F4 FREIGHT JET 0- 0
310 W AIRBUS INDUSTRIE A310 JET 167-246
314 W AIRBUS INDUSTRIE A310 N/A 222- 0
31F N AIRBUS INDUSTRIE A310 FREIGHTER JET 1- 10
312 W AIRBUS INDUSTRIE A310-200 JET 169-246
315 W AIRBUS INDUSTRIE A310-200 N/A 167-246
31X N AIRBUS INDUSTRIE A310-200 FREIGHTER JET 1- 10
313 W AIRBUS INDUSTRIE A310-300 JET 167-222
31Y N AIRBUS INDUSTRIE A310-300 FREIGHTER JET 1- 10
318 N AIRBUS INDUSTRIE A318 JET 107-117
31A N AIRBUS INDUSTRIE A318 (SHARKLETS) JET 107-117
32S N AIRBUS INDUSTRIE A318/A319/A320/A321 JET 107-220
*TRN*
)>
```

DD

Displays Universal time (Zulu Time).
Example: DD CHN

 Command Page 1

```
> dd chn
```

```
DD CHN  
CHN TIME IS 2014/0814P ON WED17JAN18  
CHN IS 02HRS 00MIN LATER  
*TRN*
```



```
>
```